



IndigoLT™ is an all-natural litter treatment
for use in poultry houses.

IndigoLT™ is safe to the environment, non-corrosive to equipment, safe and user friendly to the applicator as well as to the birds.

When applied properly, **IndigoLT™** is designed to lower ammonia levels, aid in the reduction of pathogens, disease, insect pressure, and dramatically reduce moisture in poultry litter, resulting in improved overall bird health and higher nutrient value of the litter itself.

55 Gallons (208.2 Liters)
Net Weight: 563.8 LBS. (255.7 KGS)

IndigoLT™ Application Rates:

Warm Weather Application:
Apply 32 oz. of **IndigoLT™** per 1000 sq. ft.

Cold Weather Application:
Apply 48 oz. of **IndigoLT™** per 1000 sq. ft.

Use the least amount of water possible as carrier, but enough to insure good coverage. (3.75 - 6.25-gallon water/1000 sq. ft is recommended). Mix **IndigoLT™** with water and spray immediately, no waiting period is required for product to activate.

When to Apply IndigoLT™

Apply **IndigoLT™** between batches, after cake removal, before tilling, at least 72 hours prior to bird placement. **It is important to give the product a minimum of 72 hours to work before bird placement.**

If litter is extremely damp and ammonia ridden, apply ½ rate (16 oz/1000 sq. ft. warm weather, 24 oz/1000 sq. ft. cold weather) immediately after cake removal, then apply the second half 3-5 days before bird placement.

If litter is mostly dry, or there is not enough time for a split application, apply entire amount immediately after cake removal, but no later than 3-5 days before bird placement.

Note: **IndigoLT™** is safe to apply while birds are present during the grow out.

IndigoLT™ contains: Soluble Calcium, Kelp, Humic Acid, and other natural carbon sources.

Tips to Improve Results and Product Performance:

IndigoLT™ works best when combined with the following good management practices:

- Remove cake from the poultry house after each batch.
- Till the litter after **IndigoLT™** is applied. The more times it is tilled, the better the results.
- Preheat the house a minimum of 48 hours before bird placement. Ventilate to bring in fresh air.
- On day of bird placement, ventilate at appropriate rate to insure good air quality.
- The preheat period is vital to allow **IndigoLT™** adequate time to eliminate ammonia from the house.
- It is important to prepare the litter bed immediately after bird removal to insure the driest environment possible.
- **IndigoLT™ absolutely works, but needs time to do its job.**
- Inoculate new bedding with **IndigoLT™** to ensure future results.

VERY IMPORTANT: For best results in turkey houses, till litter at least once a week.



HC 4 Box 333 • Doniphan, MO 63935
www.agrigro.com

